

Plugin settings

The credentials live centrally in the plugin, not on the individual element. You find them under *System* → *Plugins* in the entry *System - Backlinkseller*.

System - Backlinkseller

system / backlinkseller

Adds an element for Backlinkseller ad slots to the YOOtheme Pro builder. Requires Joomla 6, PHP 8.3 and YOOtheme Pro 4.5 or 5.x. No child theme needed.

Backlinkseller ID *	123456789.987654321
Page URL (Optional)	
Backlinkseller Channel	channel4.backlinkseller ▼
Cache Time (Seconds)	300
Debug Mode	☒ No ☐ Yes

Backlinkseller ID

Your ID from backlinkseller.de, for example . You find it in your Backlinkseller account. **Without it the element delivers nothing** — in debug mode a corresponding notice appears, in normal operation the slot simply stays empty.

Only digits and dots are accepted; everything else is discarded before the request.

Page URL (optional)

Backlinkseller assigns the links to a page address. Leave the field **empty** and the extension reports the address actually being requested — that is the normal case and right for most websites.

Enter a fixed address here only if all advertising slots are to be assigned to the same address regardless of the page being viewed.



A fixed address applies to the whole website. If you place the element on several pages, they all report the same address to Backlinkseller — and receive the same links.

Backlinkseller channel

The channel determines which server the request goes to: `channel1` through `channel19`. The default is `channel14`. Change the value only if Backlinkseller explicitly asks you to.

Cache time (seconds)

How long an answer once fetched is reused before asking again. Default: **300 seconds** (5 minutes), permitted are 0 to 3600.

- **Higher value:** fewer requests, faster page build, but changes at Backlinkseller take effect later.
- **0:** switches the cache off. Then every page view asks again. Useful for testing only — in production it costs noticeable time.

The cache is shared by all visitors, not kept per visitor. It is keyed by ID, page address and channel.

Debug mode

Shows the unprocessed answer of the service in the element, the entries derived from it and any error messages. **It also switches the cache off.**

Switch it on for testing only, and off again afterwards. In debug mode visitors see technical output, and every page view triggers a request of its own.

What the element itself brings along

Everything to do with appearance — list type, bullets, columns, text style, link style, separator — is set on the element in the builder, not here. See [Using the element in the builder](#).

Applies to version 2.7.5.

[Deutsche Fassung](#)

Revision #6

Created 2026-08-16 12:53:57 UTC by Norbert Graup

Updated 2026-09-07 18:24:20 UTC by Norbert Graup